
LOCAL MT5 -> TRADELOCKER

Setup Guide

From installation to your first safe copy



SuperFunded does not retain credentials or order-processing information used by this software. Use the tool at your own risk.

01 / INSTALL

Installation

Verify the downloaded files, then install the app for your Windows user.

1 Extract the ZIP

Right-click the received ZIP, choose Extract All, and open the extracted folder. Do not run the MSI from inside the ZIP. Confirm that the folder contains SuperFunded-Copier-MVP-0.11.0-Setup.msi and the English guide.

2 Run the MSI installer

In the extracted folder, double-click “SuperFunded-Copier-MVP-0.11.0-Setup.msi” and follow the on-screen steps. Keep the default install location and wait for installation to finish without closing the installer.

3 Launch from the final screen

Confirm that Launch SuperFunded Copier is checked, then select Finish. The app opens immediately. Next time, double-click the SuperFunded Copier shortcut created on the desktop.

About the unsigned build

This MSI is currently unsigned, so Windows may show an Unknown publisher warning. Confirm that it came from the provided sharing link and that the filename is correct before running it. Do not disable Windows security features.


v0.11.0 MSI SHA-256

A4B97B10FEB524D204B86EAE967EAB237315AD9D27A6298CE8DD73BB4358923B

02 / MT5

Connect MT5

Pair the desktop app and MT5 EA with the six-digit PAIR code.



- **1. Open the app**
  Use JP / EN in the top-right if needed, then note the six-digit PAIR code shown in the MT5 SOURCE card.
- **2. Allow WebRequest**
  In MT5, open Tools > Options > Expert Advisors and add http://127.0.0.1:17842 to the allowed WebRequest URLs.
- **3. Attach the EA**
  Attach SuperFundedCopierEA to one chart, enter the app's six-digit code in PairingCode, and enable AutoTrading.
- **4. Confirm connection**
  MT5 SOURCE should change to Connected. The app and MT5 must run on the same PC or VPS.


The chart symbol does not limit copying

The EA monitors all trade events in the same MT5 account, not only the symbol of the chart it is attached to. If it is attached to a USDJPY chart, EURUSD, gold, and other symbols in that account are also copied. This is a local-only tool, not a cloud copier. Run the desktop app and source MT5 on the same Windows PC or VPS. It cannot copy orders from another PC or from a PC that is not running. To prevent duplicate events, attach one EA to one chart only for each source MT5 account.

03 / TRADELOCKER

Connect TradeLocker and start

Confirm the destination account and risk settings before starting.



- **Connection details**
  Select Demo or Live, then enter server PTTSER, email, and password. Enable Save login details only if you want Windows to remember them.
- **Destination account**
  After connecting, choose the TradeLocker destination account. Start with a demo account and a small lot.
- **Copy method**
  Choose Same lot, Lot multiplier, or Balance ratio. Confirm the Stop Loss and Take Profit copy options.
- **Start and pause**
  Select Start copying. Pause stops new copies only and never closes positions that are already open.

04 / REMOTE

Using the copier on a VPS

Keep the copier running on a Windows VPS and check its status while you are away.

1 Prepare a Windows VPS

Subscribe to a VPS that provides a full Windows desktop. Keep the server address, username, and password supplied by the VPS provider. MetaTrader's built-in virtual hosting cannot run the desktop app, so use a standard Windows VPS.

2 Install MT5 and the copier on the VPS

Connect to the VPS desktop and install both the source MT5 and SuperFunded Copier on that same VPS. Attach the EA, connect it with the PAIR code, sign in to TradeLocker, then select the destination account and copy method.

3 Keep copying active on the VPS

After starting the copier, leave MT5 and the desktop app running and close the remote desktop window to disconnect. Do not sign out of the VPS or shut down Windows. If the VPS restarts, reconnect and reopen MT5 and the copier.

4 Monitor both accounts on mobile

Before leaving, sign in to MT5 Mobile and the TradeLocker mobile app or web platform so you can inspect both source and destination accounts. Mobile apps are for monitoring and manual action; the EA and copier must keep running on the Windows VPS.


Before you leave

VPS running / MT5 SOURCE connected / TradeLocker connected / Copying active / No one-sided-position warning / Demo or small lot / Signed in to both mobile platforms

05 / NOTICE

Warnings and important notice

Review these checks and important conditions before using the tool.



- **MT5 stays on Waiting**
  Check that the EA is running on a chart, the PAIR code matches, AutoTrading is enabled, WebRequest is allowed, and both apps run on the same PC or VPS.
- **TradeLocker cannot connect**
  Check Demo / Live, PTTSER, email, and password. Public API access must be available for the selected account.
- **MT5 ONLY / TL ONLY**
  A position exists on one side only. Review symbol, direction, and volume. If needed, align both accounts manually before resuming copying.

USE AT YOUR OWN RISK

Use this tool at your own discretion and risk. SuperFunded is not liable for trading losses, missed opportunities, delayed, rejected or duplicate orders, communication failures, API or platform changes, configuration errors, or any other damage arising from use of or inability to use this tool. Test thoroughly with a demo account and small lot size before live use, and monitor both MT5 and TradeLocker while it is running. Individual technical support and trading decision support are not provided for this tool.